deepseis.data.base.STEAD(directory = os.getcwd(), metadata_only = False)

A STEAD dataset object.

Parameters: directory (str, optional): path to directory where 'STEAD' folder can be found;

defaults to current working directory

metadata_only (bool, optional): if True only metadata is read to the object

Attributes: metadata: pandas.DataFrame containing metadata

waveforms: h5py object containing waveforms

deepseis.data.base.STEAD. trace_list()

A list of traces included in the STEAD dataset object.

Returns: list of traces

deepseis.data.base. STEAD. distribution(parameter, traces = None, log = False, ax = None, color = 'slategrey')

Function for plotting a distribution of parameters according to metadata.

Parameters: parameter (str): the parameter whose distribution is to be plotted, make sure this

has the same name as the corresponding columns of the metadata

traces (list, optional): if provided this plots the distribution only for the selected list

of traces

log (bool, optional): if True plots the distribution in log scale

ax (matplotlib.axes object, optional): the axes on which the histogram is to be

plotted

color (str, optional): defines the color of the bars in the resulting histogram; must be

a valid matplotlib color.

deepseis.data.base.STEAD.get_creime_data(traces = None)

Converts waveforms in the dataset to a format suitable for CREIME model (https://doi.org/10.1029/2022JB024595)

Parameters: traces (list, optional): if provided, returns data only for the selected list of traces

Returns: Xarr: numpy array of 3 component waveforms of length 512 samples.

yarr: numpy array of corresponding y-labels in format specified in

https://doi.org/10.1029/2022JB024595

deepseis.data.base.STEAD.get polarcap data(traces = None)

Converts waveforms in the dataset to a format suitable for PolarCAP model

(https://doi.org/10.1016/j.aiig.2022.08.001)

Parameters: traces (list, optional): if provided, returns data only for the selected list of traces

Returns: Xarr: numpy array consisting 64 sample windows of the vertical component centered

around the P-arrival time

deepseis.data.base.STEAD.get_creime_rt_data(traces = None , training = False)

Converts waveforms in the dataset to a format suitable for CREIME_RT model

Parameters: traces (list, optional): if provided, returns data only for the selected list of traces

training (bool, optional): if True, returns data in the format suitable for training the

model (this includes spectrograms)

Returns: Xarr: list of 3 component waveforms of random length

yarr: numpy array of corresponding y-labels in format used for CREIME RT model

deepseis.data.base.STEAD.get_dynapicker_data()

Returns data in format suitable for DynaPicker_v2, a improved model of DynaPicker (https://doi.org/10.48550/arXiv.2211.09539)

Returns: metadata: pandas.DataFrame containing metadata

waveforms: h5py object containing waveforms

deepseis.data.base.INSTANCE(directory = os.getcwd(), metadata_only = False, data = 'both')

An INSTANCE dataset object.

Parameters: directory (str, optional): path to directory where 'INSTANCE' folder can be found;

defaults to current working directory

metadata only (bool, optional): if True only metadata is read to the object

data (str, optional): can be one of the following- 'both' (both noise and events data is

included), 'noise' (only noise data is included) and 'events' (only events data is

included)

Attributes: metadata_n: pandas.DataFrame containing metadata for noise

metadata_ev: pandas.DataFrame containing metadata for events

waveforms_n: h5py object containing noise waveforms

waveforms ev: h5py object containing event waveforms

deepseis.data.base.INSTANCE.trace list noise()

A list of noise traces included in the INSTANCE dataset object.

Returns: list of noise traces

deepseis.data.base.INSTANCE.trace list events()

A list of event traces included in the INSTANCE dataset object.

Returns: list of event traces

deepseis.data.base.INSTANCE.distribution(parameter, traces = None, log = False, ax = None, color = 'slategrey')

Function for plotting a distribution of parameters according to events metadata.

Parameters: parameter (str): the parameter whose distribution is to be plotted, make sure this

has the same name as the corresponding columns of the metadata

traces (list, optional): if provided this plots the distribution only for the selected list

of traces

log (bool, optional): if True plots the distribution in log scale

ax (matplotlib.axes object, optional): the axes on which the histogram is to be

plotted

color (str, optional): defines the color of the bars in the resulting histogram; must be

a valid matplotlib color.

deepseis.data.base.INSTANCE.get_creime_data(traces_n = None, traces_ev = None)
Converts waveforms in the dataset to a format suitable for CREIME model
(https://doi.org/10.1029/2022JB024595)

Parameters: traces_n (list, optional): if provided, returns data only for the selected list of noise

traces

traces_ev (list, optional): if provided, returns data only for the selected list of event

traces

Returns: Xarr: numpy array of 3 component waveforms of length 512 samples.

yarr: numpy array of corresponding y-labels in format specified in

https://doi.org/10.1029/2022JB024595

deepseis.data.base.INSTANCE.get_polarcap_data(traces = None, training = False)
Converts waveforms in the dataset to a format suitable for PolarCAP model
(https://doi.org/10.1016/j.aiig.2022.08.001)

Parameters: traces (list, optional): if provided, returns data only for the selected list of traces

training (bool, optional): if True, returns data in the format suitable for training the

model

Returns: Xarr: numpy array consisting 64 sample windows of the vertical component centered

around the P-arrival time

yarr: numpy array containing 'trace_polarity' according to metadata

deepseis.data.base.INSTANCE.get_creime_rt_data(traces_n = None, traces_ev =
None, training = False)

Converts waveforms in the dataset to a format suitable for CREIME_RT model

Parameters: traces_n (list, optional): if provided, returns data only for the selected list of noise

traces

traces ev (list, optional): if provided, returns data only for the selected list of event

traces

training (bool, optional): if True, returns data in the format suitable for training the

model (this includes spectrograms)

Returns: Xarr: list of 3 component waveforms of random length

yarr: numpy array of corresponding y-labels in format used for CREIME_RT model

deepseis.data.base.INSTANCE.get_dynapicker_data(event_type='EQ')

Returns data in format suitable for DynaPicker_v2, an improved version of DynaPicker model (https://doi.org/10.48550/arXiv.2211.09539)

Parameters: event_type (str, optional): if 'EQ' (default), returns data corresponding to events, else

returns data corresponding to noise

Returns: metadata: pandas.DataFrame containing metadata

waveforms: h5py object containing waveforms

Real Data

deepseis.data.realdata.waveform_download(wsp, net, sta, loc, chan, starttime, endtime)

This function allows user to download continuous waveform data using the <u>Obspy get_waveforms</u> function.

Parameters: wsp (str): FDSN Web service request client

(https://docs.obspy.org/packages/autogen/obspy.clients.fdsn.client.Client.html)

net (str): the network code for the seismic network from which the waveform is

to be downloaded

sta (str): the station code for the seismic station from which the waveform is to

be downloaded

loc (str): location identifier for downloading the data

chan (str): channel code for downloading data

starttime (UTCDateTime): starting time for the downloaded data

endtime (UTCDateTime): ending time for the downloaded data

Returns: stream: downloaded Obspy Stream

deepseis.data.realdata.preprocessing(stream, resample_freq=100, freq_min=1, freq_max=45)

This function is used to pre-process downloaded data; pre-processing steps include resampling, detrending and bandpass filtering

Parameters: stream (obspy Stream): stream object for preprocessing

resample_freq (float, optional): frequency (Hz) at which the stream is to be

resampled

freq min (float, optional): lower frequency (Hz) limit for bandpass filtering

freq max (float, optional): upper frequency (Hz) limit for bandpass filtering

Returns: resample_stream: resampled and detrended stream object

X: bandpass filtered data in the form of numpy array

deepseis.models.creime.CREIME

A **CREIME** object.

Attributes: model: keras Model trained as described in https://doi.org/10.1029/2022JB024595

deepseis.models.creime.CREIME.get_model(untrained = False)

Parameters: untrained (bool, optional): if True, returns untrained model

Returns: model: keras Model for <u>CREIME</u>

deepseis.models.creime.CREIME.predict(X)

Parameters: X: numpy array of shape 512 × 3 representing 3-component seismograms on which

CREIME is to be applied

Returns: y_pred: numpy array of corresponding predicted labels in the shape 512 × 1

predictions: list of tuples with three elements corresponding to noise-vs-event classification (0 for noise and 1 for event), predicted magnitude (for events) and

predicted P-arrival sample (for events)

deepseis.models.creime.CREIME_RT

A CREIME_RT object, which is an improved version of <u>CREIME</u> capable of handling data in real time.

Attributes: model: keras Model for CREIME_RT

deepseis.models.creime.CREIME RT.get model(untrained = False)

Parameters: untrained (bool, optional): if True, returns untrained model

Returns: model: keras Model for CREIME_RT

deepseis.models.creime.CREIME RT.predict(X)

Parameters: X: list of 3-component seismograms of length 6000 samples or less on which

CREIME_RT is to be applied

Returns: $y_pred:$ numpy array of corresponding predicted labels in the shape 6000×1

predictions: list of tuples with two elements corresponding to noise-vs-event classification (0 for noise and 1 for event) and predicted magnitude (for events)

deepseis.models.polarcap.PolarCAP

A PolarCAP object.

Attributes: model: keras Model trained as described in

https://doi.org/10.1016/j.aiig.2022.08.001

deepseis.models.polarcap.PolarCAP. get_model(untrained=False)

Parameters: untrained (bool, optional): if True, returns untrained model

Returns: model: keras Model for PolarCAP

deepseis.models.polarcap.PolarCAP. predict(X)

Parameters: X: numpy array of shape 64 × 1 consisting of vertical component of seismograms

centered around the P-arrival sample

Returns: predictions: list of tuples of two elements representing the polarity and the

probability of the prediction

DynaPicker

deepseis.models.dynapicker.load model(path)

Loading pretrained DynaPicker_v2 model.

Parameters: path (str): path of the entire pretrained PyTorch model e.g., './checkpoint.pt'

deepseis.models.dynapicker.arguments()

parameter setting up for DynaPicker v2 training.

Parameters: batch size (int): the hyperparameter that defines the number of samples used in

each iteration

Ir (float): learning rate

epochs (int): epoch number

num classes (int): classes numbers

patience (int): how many epochs to wait after last time validation loss improved

verbose (boolean): if True, prints a message for each validation loss improvement

when using early stopping

model_save_path (str): the path to save trained model

deepseis.models.set_seed(seed)

This function is used to ensure that results are reproducible.

Parameters: seed (int): seed value

Modules

deepseis.modules.phaseclassification.CustomDataset(dataset)

This function allows user to create phase classification dataset in torch format.

Parameters: dataset (numpy.array): dataset including data and label

deepseis.modules.phaseclassification.train(args, device, Train_Loader, Valid_Loader, criterion, optimizer, scheduler=None)

This function allows user to train DynaPicker_v2 on the created dataset with using early stopping.

Parameters: args: argparse module's support for command-line interfaces

device (torch.device or int): selected device for running PyTorch model on gpu/cpu

Train_Loader (torch.DataLoader): training PyTorch DataLoader instance

Valid_Loader (torch.DataLoader): validation PyTorch DataLoader instance

criterion: PyTorch loss function that determine the model'performance by

comparing predictions with ground truth

optimizer: PyTorch optimizer that adjusting model parameters to reduce model error in each training step.

in each training step

scheduler: PyTorch learning rate scheduler that adjust the learning rate based on

the number of epochs, default is None

deepseis.modules.phaseclassification.test(args, device, model, Test_Loader, criterion)
This function allows user to test DynaPicker v2 on the created dataset.

Parameters: args (function): argparse module's support for command-line interfaces

device (torch.device or int): selected device for running PyTorch model on gpu/cpu

model: pre-trained PyTorch model

Test Loader (torch.DataLoader): Testing PyTorch DataLoader instance

criterion: PyTorch loss function that determine the model'performance by

comparing predictions with ground truth

deepseis.modules.pytorchtools.EarlyStopping(patience=5, verbose=False, delta=0, path=", trace_func=print)

A tool to use early stopping to deal with overfitting in PyTorch. Code source from https://github.com/Bjarten/early-stopping-pytorch.

Parameters: patience (int): how long to wait after last time validation loss improved

verbose (boolean): If True, prints a message for each validation loss improvement.

delta (float): minimum change in the monitored quantity to quality as an

improvement

path (str): path for the checkpoint to be saved to

trace_func (function): trace print function

Packagetools

deepseis.utils.packagetools.monitor1(wsp, network, station, location, channel, start_time, end_time, device, leng_win, shift=10, picker_num_shift=1, save_result=False, path='./', file_name=None)

This function allows user to download and monitor continuous waveform data.

Parameters: wsp (str): FDSN Web service request client

(https://docs.obspy.org/packages/autogen/obspy.clients.fdsn.client.Client.html)

network (str): the network code for the seismic network from which the

waveform is to be downloaded

station (str): the station code for the seismic station from which the waveform is

to be downloaded

location (str): location identifier for downloading the data

channel (str): channel code for downloading data

start_time (UTCDateTime): starting time for the downloaded data

end_time (UTCDateTime): ending time for the downloaded data

For more details on above parameters refer to

https://docs.obspy.org/packages/autogen/obspy.clients.fdsn.client.Client.get_waveforms.html

device (torch.device or int): selected device for running PyTorch model

leng_win (int): length of window used for picking body-wave arrival times

shift (*int, optional*): shift between subsequent time windows fed to CREIME_RT for event detection

picker_num_shift (*int, optional*): shift between subsequent time windows for which DynaPicker_v2 calculated picking probabilities

save_result (bool, optional): if True, the results of the monitoring process are saved in a .csv file

path (str, optional): path to directory where csv file is to be saved

file_name (str): name of csv file where the results are saved, must be provided if

save_result is set to True

Returns:

outputs: A dictionary with P-picks, S-picks, magnitudes and first-motion polarities

corresponding to detected events

deepseis.utils.packagetools.monitor2(path_to_stream, device, leng_win, format=None, shift = 10, picker_num_shift = 10, save_result = False, path = './', file_name = None)

This function allows user to download and monitor continuous waveform data.

Parameters:

path_to_stream (*str*): the path to the downloaded data file, to be read as a stream using documents.org/d

device (torch.device or int): selected device for running PyTorch model

leng_win (int): length of window used for picking body-wave arrival times

format (str, optional): format of the file being read

shift (*int, optional*): shift between subsequent time windows fed to CREIME_RT for event detection

picker_num_shift (*int, optional*): shift between subsequent time windows for which DynaPicker_v2 calculated picking probabilities

save_result (bool, optional): if True, the results of the monitoring process are saved in a .csv file

path (str, optional): path to directory where csv file is to be saved

file_name (*str*): name of csv file where the results are saved, *must* be provided if save_result is set to True

Returns:

outputs: A dictionary with P-picks, S-picks, magnitudes and first-motion polarities corresponding to detected events

deepseis.utils.packagetools.classic_picking(trigger_type, trace, nsta, nlta, thr_on, thr_off, plotFlag)

This function allows classic event detection using short time average/long time average (sta/lta) algorithm.

Parameters:

trigger_type (*str*): this should be either 'classic_sta_lta' or 'recursive_sta_lta' which imports the corresponding function from obspy.signal.trigger

trace (obspy trace): this is the trace on which sta/lta is to be applied

 ${\it nsta} \ ({\it int}) : {\it length} \ of \ window \ ({\it in \ samples}) \ for \ computing \ short \ time \ average$

nlta (int): length of window (in samples) for computing long time average

thr_on (float): threshold at which trigger is switched on

thr_off (float): threshold at which trigger is switched off

plotFlag (*bool*): if True the characteristic function of the trigger is plotted on the waveform using the <u>obspv.signal.trigger.plot_trigger</u> function

Picktools

deepseis.utils.picktools.make stream stead(dataset)

This function allows user to convert STEAD dataset from hdf5 to obspy stream (code source from https://github.com/smousavi05/STEAD)

Parameters: dataset (hdf5): hdf5 dataset

deepseis.utils.picktools.make_stream_instance(df, h5, line, wftype)

This function allows user to convert INSTANCE dataset from hdf5 to obspy stream (code source from https://github.com/INGV/instance)

Parameters: df (pandas DataFrame): metadata of INSTANCE dataset

line (int): line number of the hdf5 File

wftype (str): waveform type 'ev_c', 'ev_gm' or 'noise' for events in counts,

events in ground motion units or noise, respectively

deepseis.utils.picktools.phase_picking(device, model, st, bandpass_filter_flag, picker_num_shift, batch_size, fremin, fremax, fo, fs)

This function allows user to apply DynaPicker_v2 for phase picking on continuous waveform.

Parameters: device (torch.device or int): selected device for running PyTorch model

model: PyTorch model for DynaPicker v2

stream (obspy stream): obspy stream format of the data used for phase picking

band passfilter flag (boolean): if Ture, apple band pass filter

picker_num_shift (*int, optional*): shift between subsequent time windows for which DynaPicker_v2 calculated picking probabilities

batch_size (*int, optional*): the hyperparameter that defines the number of samples used in each iteration for phase arrival time estimation

fremin (int): pass band low corner frequency.

fremax (int): pass band high corner frequency.

fo (int): filter order

fs (int): sampling rate n Hz, default value is 100

Visualizations

A set of tools for visualizing waveform data and model outputs.

deepseis.utils.visualizations.plot_waveform(data, times=None, P_arr=None, S_arr=None, magnitude=None)

Tool for visualizing 3 component seismic waveforms.

Parameters: data (numpy array): 3-component waveform in the form of numpy array

times (list or numpy array, optional): a list of times (in samples) corresponding to the

data provided

P_arr (int): P-arrival sample

S arr (int): S-arrival sample

magnitude (float): magnitude of the event

deepseis.utils.visualizations.plot_creime_data(X,y, y_pred=None)

This is a visualization tool for data, labels and outputs corresponding to **CREIME**.

Parameters: X (numpy array): numpy array of shape 512 × 3 representing 3-component

seismograms

y (numpy array): numpy array of shape 512 × 1 representing corresponding CREIME

label

y_pred (numpy array, optional): numpy array of shape 512 × 1 representing

corresponding CREIME prediction

deepseis.utils.visualizations.plot creime rt data(X,y, y pred=None)

This is a visualization tool for data, labels and outputs corresponding to CREIME_RT.

Parameters: X (numpy array): numpy array of variable length representing 3-component

seismograms

y (numpy array): numpy array of shape 6000 × 1 representing corresponding

CREIME RT label

y_pred (numpy array, optional): numpy array of shape 6000 × 1 representing

corresponding CREIME prediction

deepseis.utils.visualizations.plot polarcap data(X, y true=None, y pred=None)

This is a visualization tool for data, labels and outputs corresponding to PolarCAP.

Parameters: X ($numpy \ array$): numpy array of shape 64×1 representing the vertical component

of seismograms centered around the P-arrival sample

y_true (str, optional): the 'known' first-motion polarity

y_true (tuple or list, optional): the predicted first-motion polarity and corresponding

probability

deepseis.utils.visualizations.plot_dynapicker_stead(stream, dataset, prob_p, prob_s, picker_num_shift, figure_size, index)

This is a visualization tool for plotting STEAD data and outputs corresponding to DynaPicker_v2.

Parameters: stream (obspy.core.stream.Stream): obspy stream

dataset (hdf5 dataset): STEAD dataset

prob_p (float): probability of the estimated P-phase

prob_s (float): probability of the estimated S-phase

picker_num_shift (*int, optional*): shift between subsequent time windows for which

DynaPicker v2 calculated picking probabilities

figure_size (tuple): figure size

index (int): index of the seismic waveform component, e.g., 0 - 'E-W', 1 - 'N-S' or 2 -

'Vertical'

deepseis.utils.visualizations.plot_dynapicker_instance(stream, row, prob_p, prob_s, picker_num_shift, index, figure_size)

This is a visualization tool for INSTANCE data and outputs corresponding to DynaPicker_v2.

Parameters: stream (obspy.core.stream.Stream): obspy stream

row: INSTANCE dataset

prob_p (float): probability of the estimated P-phase

prob_s (float): probability of the estimated S-phase

picker_num_shift (int, optional): shift between subsequent time windows for which

DynaPicker_v2 calculated picking probabilities

figure_size (tuple): figure size

deepseis.utils.visualizations.plot_dynapicker_stream(stream, prob_p, prob_s, picker_num_shift, figure_size)

This is a visualization tool for stream data and outputs corresponding to DynaPicker_v2.

Parameters: stream (obspy.core.stream.Stream): stream data

prob_p (float): probability of the estimated P-phase

prob_s (float): probability of the estimated S-phase

picker_num_shift (int, optional): shift between subsequent time windows for which

DynaPicker_v2 calculated picking probabilities

figure_size (tuple): figure size

deepseis.utils.visualizations.plot_dynapicker_train_history(train_loss, valid_loss, figure_size)

This is a visualization tool for plotting DynaPicker_v2 training history

Parameters: train_loss(list): loss of training dataset per epoch

valid_loss(list): loss of validation dataset per epoch

figure_size (tuple): figure size

deepseis.utils.visualizations.plot_dynapicker_confusionmatrix(y_true, y_pred, label list,figure size, cmap)

This is a visualization tool for plotting confusion matrix using DynaPicker_v2 for phase classification.

Parameters: y_true (*list*): ground truth labels

y_pred (list): predicted labels

label_list (list): list of class label like ['P-phase', 'S-phase', 'Noise']

figure_size (tuple): figure size in inches

cmap: colormaps in Matplotlib

deepseis.utils.visualizations.plot_precision_recall_curve(y_true, y_pred, y_pred_prob, label_list, figure_size)

This is a visualization tool for plotting confusion matrix using DynaPicker v2 for phase classification.

Parameters: y true (*list*): ground truth labels

y pred (list): predicted labels

y_pred_prob (list): probabilities for each data

label_list (list): list of class label like ['P-phase', 'S-phase', 'Noise']

figure_size (tuple): figure size in inches

deepseis.utils.visualizations.plot_roc_curve(y_true, y_pred, y_pred_prob, label_list, figure_size)

This is a visualization tool for plotting ROC curve..

Parameters: y_true (*list*): ground truth labels

y_pred (list): predicted labels

y_pred_prob (list): probabilities for each data

label list (list): list of class label like ['P-phase', 'S-phase', 'Noise']

figure_size (tuple): figure size in inches